## Installation Guide for Python, Visual Studio Code, and Anaconda

## 0. MacOS Users - NOTICE: MUST READ!!!

Since we're installing multiple packages, we'll need to use a tool called a package manager. For macOS, we'll use the Homebrew package manager. Follow these steps to install Homebrew:

- 1. Open the Terminal app.
- 2. Install Homebrew by running the following command:

```
/bin/bash -c "$(curl -fsSL
https://raw.githubusercontent.com/Homebrew/install/HEAD/install.sh)"
```

3. Verify the installation:

```
brew --version
```

4. Update Homebrew to ensure you have the latest formulae:

```
brew update
```

Once Homebrew is installed, you can proceed with the steps outlined below for installing Python, Visual Studio Code, and Anaconda.

# 1. Installing Python

#### macOS

- 1. Open the Terminal.
- 2. Run the following command to install Python:

```
brew install python
```

3. Verify the installation:

```
python3 --version
```

#### Windows

- Using winget:
  - 1. Open Command Prompt or PowerShell.
  - 2. Run the following command:
    - winget install -e --id Python.Python.3
  - 3. Verify the installation:
    - python --version
- Using the Installer:
  - 1. Visit the official Python website.
  - 2. Download the installer for Windows.
  - 3. Run the installer *and check* "Add Python to PATH" during the setup.
  - 4. Complete the installation and verify as above.

#### Linux

- RHEL-based (e.g., Fedora, RedHat, CentOS, etc):
  - 1. Open the Terminal.
  - 2. Run the following commands:
    - sudo dnf install python3
  - 3. python3 --version
- Debian-based (e.g., Ubuntu, Mint, etc):
  - 1. Open the Terminal.
  - 2. Run the following commands:
    - sudo apt update
    - sudo apt install python3
    - python3 --version

## 2. Installing Visual Studio Code

#### macOS

- 1. Open the Terminal.
- 2. Run the following command:

brew install --cask visual-studio-code

#### Windows

- Using winget:
  - 1. Open Command Prompt or PowerShell.
  - 2. Run the following command:
    - winget install -e --id Microsoft.VisualStudioCode
- Using the Installer:
  - 1. Visit the Visual Studio Code website.
  - 2. Download the appropriate installer for Windows.
  - 3. Run the installer and follow the setup instructions.

#### Linux

- RHEL-based:
  - 1. Download the RPM package from the Visual Studio Code website.
  - 2. Install it using:
    - sudo rpm -i code\*.rpm
  - 3. Verify installation:
  - 4. code --version
- Debian-based:
  - 1. Download the DEB package from the Visual Studio Code website.
  - 2. Install it using:
    - sudo dpkg -i code\*.deb
    - sudo apt-get install -f
  - 3. Verify installation:
  - 4. code --version

## 3. Installing Anaconda

#### macOS

- 1. Open the Terminal.
- 2. Run the following command:

```
brew install --cask anaconda
```

## Windows

- Using winget:
  - 1. Open Command Prompt or PowerShell.
  - 2. Run the following command:
    - winget install -e --id Continuum.Anaconda3
- Using the Installer:
  - 1. Download the installer from the official website.
  - 2. Run the installer and follow the setup instructions.
  - 3. Verify installation:

■ conda --version

## Linux

- 1. Download the Linux installer from the official website.
- Open the Terminal and navigate to the download directory.
   Run the installer:

```
bash Anaconda3*.sh
```

- 4. Follow the on-screen instructions to complete the installation.
- 5. Verify installation:

```
conda --version
```